### **ECUMASTER SERIAL PROTOCOL**

```
Communication is based on standard RS232 at 19200,n,8,1
Each data frame consits of 5 bytes:

typdef struct
{
    ubyte channel;
    ubyte idChar;
    ubyte valueH;
    ubyte valueL;
    ubyte checksum;
}
```

#### CHANNEL

```
Channel is a number that defines what kind of data is sent.

The channels are defined in xml log files. These files are located in EMU install directory:

XML\LOG\version1_xxx.xml, where xxx defines EMU firmware version.
```

#### Sample channel definition:

```
<symbol name="RPM" storage="word" type="value" divider = "1" unit="RPM"
group="Basic" gauge="1" gaugeMin="0" gaugeMax="9000" tick="1000" gaugeDiv="1000" color="1"
priority="1" channel="1"> </symbol>
```

```
name - name of channel
storage - data size
```

word	unsigned 16 bits
sword	signed 16 bits
ubyte	unsigned 8 bits
Sbyte	signed 8 bits

Type — data type

value	value
ParamList:	Listed type

Example of listed type (bitfield=1" means that given name is represented by bit defined by value)

```
<paramlist name="checkEngine" bitfield="1">
<list name="NONE"</pre>
                                                         value="0"> </list>
<list name="CLT"</pre>
                                                         value="1"> </list>
<list name="IAT"</pre>
                                                         value="2"> </list>
<list name="MAP"</pre>
                                                         value="3"> </list>
<list name="WBO"</pre>
                                                         value="4"> </list>
<list name="EGT1"</pre>
                                                         value="5"> </list>
                                                         value="6"> </list>
<list name="EGT2"</pre>
                                                         value="7"> </list>
<list name="EGT ALARM"</pre>
<list name="KNOCK"</pre>
                                                         value="8"> </list>
                                                         value="9"> </list>
<list name="FF SENSOR"</pre>
<list name="DBW"</pre>
                                                         value="10"> </list>
<list name="FPR"</pre>
                                                         value="11"> </list>/paramlist>
```

```
divider - the final channel value is calculated as follow:
FinalValue = value / divider
unit - unit of the channel
gaugeMin, gaugeMax - the maximum / minimun value of the channel
precision - number of displayed decimal places
channel - the channel index
```

### **IDCHAR**

The constant always equal to 0xA3

# VALUEH /VALUEL

Low and high byte of the channel value

## **CHECKSUM**

The sum of CHANNEL, IDCHAR, VALUEH, VALUEL modulo 255